
Step-by-step test procedure – τ-Argus


This document provides a step-by-step procedure to test the main features of τ -Argus. This test procedure uses the dataset provided in the installation package to compute two tables and applies modular and hypercube method to protect these. It uses τ -Argus 4.1.7b4.

a) Open τ -Argus. Use File Open microdata, or the yellow folder icon and select tau_testW.asc that should be in the data folder where you unzipped τ -Argus.

The metadata (.rda file) is placed in the same folder and τ -Argus should see that and select it automatically.




b) Use the Specify tables icon.




c) And specify two tables.


The first one using the explanatory variables IndustryCode and Region and the response variable Var1, using two rules: dominance rule (n=1,k=85) and frequency rule (3, 10%). The second one using the same explanatory variables but the response variable <freq> instead of Var1, using only the frequency rule.




d) τ -Argus will explore the dataset, make the tables and apply the primary rules. Select Modular, then click Supress.



e) Click OK on the next box.




f) τ -Argus will work a few seconds.




g) Then will show the number of suppressed cells.




h) Use the Table summary button to verify that you get these results :




i) Click on the Save Table icon




j) Use Code-value and choose where you want to save the file on your computer.



k) τ -Argus will show the report. Verify that the coding tree for both variables IndustryCode and Region have been used and are detailed in the report.



l) Verify that you have both the report saved as an .html file, and the output saved as a .txt file with the suppressed cells marked with "x"









test.html test.txt


m) Go back to τ-Argus and click on the Select Table icon.




n) Choose the second tabulation with the <freq> response variable.




o) And apply the hypercube method.




p) Leave the default options on the GHMiter specifications box.



q) τ-Argus GHMiter method will take a few seconds to work.



r) Then τ -Argus will provide the number of cells suppressed.



s) Use the Table summary button to verify that you get these results.

